



Model Number: Bed Bug Cleaning

San Antonio Bed Bug and Lice Mattress Cleaning Rental Service / Chemicals + Equipment

Manufacturer: SteamBrite MFG

San Antonio, TX BedBug Treatment Service

Do-It-Yourself or Professional application and or cleaning service.

Professional Service

Service can include application spray only or cleaning with application spray.

MicroBan Bed Bug Flyer

Plus Materials MicroBan X590 (to purchase the products click [HERE](#))

Do-it-Yourself equipment rental \$40 per day + MicroBan X590

Service Call \$35.00 (Listed above as Estimated Shipping Cost. // Add \$0.55 a mile round trip for outlying counties).

Will drop off rental equipment at job site. (2x service calls needed if dropping off and picking up.)

Pick and deliver of equipment at:

SteamBrite Supply, 18975 Marbach Lane #200-C off Nacogdoches Rd, San Antonio, Tx 78266

Service Area include:

Texas Cities:

San Antonio Texas, Kirby, Lion Valley, Converse, Live Oak, Universal City, Schertz, New Braunfels, Pleasanton, Sequin, Canyon Lake, Hondo, San Marcos, Kyle, Kerrville, Lockhart

Texas Counties:

Bexar, Atascosa, Bandera, Comal, Guadalupe, Kendall, Medina, Wilson

Microban® X-580 Institutional Spray Plus (soon to be called X-590)

The Microban® treatment on water losses is recognized by major insurance companies!

Water-based, bactericide, fungicide, deodorant, and insecticide all in one unique formulation. One application kills insects, mold, mildew, bacteria odors, and provides long lasting residual protection. Microban® is E.P.A. approved for many decontamination applications including: sewage backups, removal of carcasses, etc. Microban® X-580 Institutional Spray Plus kills gram negative bacteria, the bacteria encountered in sewage backups and toilet overflow situations.

Microban® X580 Institutional Spray Plus is E.P.A. approved for both spray and ULV fog application. Microban® X-580 Institutional Spray Plus kills roaches, fleas, ants, beetles, bedbugs, and their larvae. Microban® X-580 Institutional Spray Plus

protects stored fabrics against textile destroying insects for 6 months! You best resource for bedbug prevention is Microban X-580 with regular fabric cleaning.

Mixing: Use full strength. Do not dilute. Refer to label..

Application: Apply via sprayer to porous surfaces at a rate of 1,500 square feet per gallon. Spray until moist, brush into carpeting, and allow 10-20 minutes for drying. See label for additional instructions.

New label is also available (photo to right.) Same product. As a dealer we can order the label of choice so we want to let you know we do not guarantee the label we will ship. Either way, same stuff on the inside.

MSDS

Microban X-580 Label

Bedbug Resources:

Definition of Bed bug

Bed Bug Bite Treatment

Bed Bug Symptoms

Bed Bug eggs Pictures

Bedbug Registry

Bed Bug Pictures

Bedbugs Plague Wisconsin

US Environmental Protection Agency (EPA) Bed Bug Information

also marketed under part number 4GHW1

GENERAL METHOD OF APPLICATION

Surfaces and objects must be cleaned of gross dirt with suitable detergent before treatment. Spray surfaces and articles until thoroughly wet, use enough so that treated

surfaces and objects remain wet for at least 10 minutes. May be applied with a sponge to pre-cleaned, hard non-porous surfaces, allowing to dry for 10 minutes. For fogging and other large volume applications use appropriate spraying equipment,

protective clothing, gloves and respirator. Heavily treated spaces should be adequately

ventilated and not re-entered for at least one hour after treatment.

AS A MILDEWCIDE, FUNGICIDE AND BROAD SPECTRUM DISINFECTANT: (Kills most gram negative and gram positive bacteria and influenza virus). In hospitals, operating rooms, emergency rooms, lobbies, hallways, patient rooms, wards, washrooms, scrub stations, mop rooms, morgues, pathology labs, nurse's stations, laboratories, veterinary clinics and other health care facilities; in schools, hotels, motels, restaurants, offices, homes and industrial buildings. For use on pre-cleaned hard non-porous surfaces such as glazed tiled porcelain, waste receptacles, compactors, on, in and around rest room fixtures, toilet seats, locker rooms, telephones, door knobs, hospital apparatus and equipment, furniture and empty containerized storage units. For athlete's foot fungus on floors, shower stalls and rest rooms. Follow method of application specified above.

AS A BACTERIOSTAT, FUNGISTAT AND DEODORIZING AGENT

Apply Microban Formula X-580 Institutional Spray Plus as directed to floors, walls, ceilings that have been damaged by smoke, fire, floods and sewage backups. For cleanup operations in areas such as attics, wall voids, basements, areas above suspended ceilings and similar inaccessible spaces in buildings. Spray avian, rodent and other animal and human wastes and carcasses as directed above, prior to removal and disposal. Treat spaces and surfaces as specified in method of application. For use as a bacteriostat, fungistat and deodorizing agent on carpeting found in schools, hotels, motels, homes, shelters, commercial, industrial and public buildings. After flood or water damage, vacuum or extract as much water as possible before application. Apply full strength with sprayer until moist to carpet nap and rake or brush in. To treat the backing and padding a fogger is recommended. Allow to remain until dry. For best results, carpets should be cleaned before application.

This product is not to be used as a terminal sterilant/high level disinfectant on any surface or instrument that (1) is introduced directly into the human body, either into or in contact with the bloodstream or normally sterile areas of the body, or (2) contacts intact mucous membranes but which does not ordinarily penetrate the blood barrier or otherwise enter normally sterile areas of the body. This product may be used to pre-clean or decontaminate critical or semi-critical medical devices prior to sterilization or high level disinfection.

TO DISINFECT FARM PREMISES, POULTRY HOUSES, ANIMAL PENS AND VEHICLES

Remove all animals and feed from premises, vehicles and enclosures. Remove all litter and manure from floors, walls and surfaces of barns, pens, stalls, chutes and other facilities and fixtures occupied or traversed by animals. Empty all troughs, racks and other feeding and watering appliances. Thoroughly clean all surfaces with soap or detergent and rinse with water. Saturate all surfaces with the recommended disinfecting solution for a period of 10 minutes. Immerse all halters, ropes and other types of equipment used in handling and restraining animals, as well as forks, shovels and scrapers used for removing litter and manure. Ventilate buildings, cars, boats and other closed spaces. Do not house livestock or employ equipment until treatment has been absorbed, set or dried. Thoroughly scrub all treated feed racks, mangers, troughs, automatic feeders, fountains and waterers, with soap or detergent and rinse with potable water before

reuse. Apply Microban Formula X-580 Institutional Spray Plus full strength as directed in general method of application until thoroughly wet. Allow all surfaces to dry thoroughly, ventilate enclosed spaces adequately. Do not house animals in treated areas until thoroughly dry and free from odors.

PHYSICAL AND CHEMICAL HAZARDS

Flammable. Keep away from heat and open flame.

STORAGE AND DISPOSAL (for nonresidential, nonhousehold containers)

Do not contaminate water, food or feed by storage and disposal.

PESTICIDE STORAGE: Keep from freezing. Store in ventilated areas.

PESTICIDE DISPOSAL: Wastes resulting from the use of this product may be disposed of on site or at an approved waste disposal facility.

CONTAINER DISPOSAL: Triple rinse (or equivalent). Then offer for recycling or reconditioning, or puncture and dispose of in a sanitary landfill, or incineration, or, if allowed by state and local authorities, by burning. If burned, stay out of smoke.

STORAGE AND DISPOSAL (for household/residential containers)

IF EMPTY: Do not reuse this container. Place in trash or offer for recycling if available.

IF PARTLY FILLED: Call your local solid waste agency or 1-800-CLEANUP for disposal instructions. Never place unused product down any indoor or outdoor drain.

DIRECTIONS FOR USE

It is a violation of Federal Law to use this product in a manner inconsistent with its labeling.

Microban Formula X-580 Institutional Spray Plus should be applied with hand or power operated sprayers, foggers, automated metering systems or gravity drip dispensers as an insecticide, bactericide, mold and mildewcide, fungicide and deodorizing agent, to previously cleaned surfaces. Spray areas until thoroughly moist, giving special attention to cracks and crevices. Allow ten to twenty minutes for drying. It is not necessary to wipe the sprayed surface. Microban Formula X-580 Institutional Spray Plus should not stain those materials not stained by water.

Remove pets, birds, and cover fish aquariums before spraying.

Direct and repeat spraying of Ants, Roaches, Bedbugs, Silverfish and other harmful insects and in the cracks, crevices and hidden surfaces

where they hide are necessary for control. Apply every 28 days or as often as needed.

To Kill Fleas and Ticks: Remove and destroy old animal bedding. Spray sleeping quarters of animals, floor areas, around baseboards, window and door frames, cracks, crevices and wherever the presence of these insects are suspected. Repeat as necessary. Thoroughly vacuum rugs and carpets prior to application. Do not spray animals. Put fresh bedding in animal quarters after spray has dried. Treat animals with a registered flea and tick control product before allowing them to enter treated area.

To Kill Sowbugs, Centipedes, Firebrats and Mites: Contact as many insects as possible with the spray. Also thoroughly spray all parts of the room suspected of harboring these pests. Special attention should be paid to cracks, crevices, hidden surfaces under sinks, basement and utility rooms, floors, doorjams, behind and under stoves and refrigerators.

To Kill Flies, Mosquitoes, Gnats and Wasps: Close all doors and windows and spray upward into center of room with a slow sweeping motion.

Spray 5-10 seconds for average room. Keep room closed for 15 minutes after spraying. Ventilate room thoroughly before re-entry. Sweep up and destroy fallen insects. Before spraying cover exposed food and utensils.

To Kill Carpet Beetles, Lice and Moths: Clean all articles prior to application.

Thoroughly spray top and undersides of rugs and carpets.

Thoroughly spray the interiors of lockers, trunks, closets, cupboards and other storage areas. Spray directly on restroom fixtures. When treating upholstered furniture and mattresses thoroughly spray exterior, paying particular attention to seams and folds. Interior should be treated to eliminate hidden infestations.

Microban Formula X-580 Institutional Spray Plus when used as directed is effective in decontaminating the treated exposed surfaces of bedding, mattresses, textiles, drapes, upholstered furniture, rugs, carpets and in storage areas to control mold, mildew, fungus, insects and odors wherever they are a problem.

Microban X-580 is effective against these and many other:

Insects:

- Fleas
- Ticks
- Lice
- Bedbugs
- Mites
- Roaches

Fungi:

- Aspergillus niger (Black Mold)
- Aspergillus flavus
- Aspergillus terreus
- Penicillium citrinum
- Athletes' foot fungi

Viruses:

- Influenza A2
- Herpes simplex 2 - Genital herpes

Bacteria:

- Staphylococcus aureus
- Staphylococcus albus
- Staphylococcus aureus hemolyticus coagulase
- Salmonella choleraesuis
- Escherichia coli
- Staphylococcus pyogenes aureus
- Staphylococcus albus coagulase
- Staphylococcus citreus
- Salmonella typhosa
- Pseudomonas aeruginosa

Equipment: Carpet Cleaning Machines > Vacuum Cleaners > HEPA Concrete Dust Slurry Hazmat Vacuums >

• Most gram-positive and gram-negative bacteria

Why Use SteamBrite ?

Over 30 Years Of Experience

Over 20,000,000 Sq. Ft.Of Property Restored

San Antonio First IICRC Certified Master Cleaning and Master Restoration Firm
(1990)

Certified Indoor Air Quality Specialist

Certified Odor Control Technician

Certified Fire Damage Technician

Certified Water Damage Technician

Certified Advanced Water Damage Technician

Certified Upholstery Cleaning

Certified Senior Claim Inspector (Highest Achievable Certification For The Cleaning
and Restoration Industry, Certified Expert Witness For Court Case Resolution)

Certified IICRC Schooling Location

Certified IICRC Continuation Credits Training Center

South Texas Largest Supply Center for Specialty Cleaning Supplies and

Do-It-Yourself Rentals

San Antonio Bed Bug and Lice Mattress Cleaning Service

Availability: This product was added to our catalog on Tuesday 24 July, 2012